

# How to add a License to Idemia Product



11/12/2020



# Requirements

**MorphoManager install Morpho License Manager as part of the package**

**If not using Morphomanager**

**Download Morpho License Manager and install**

**[https://service.morphotrak.com/content/software/License%20Manager/Morpho\\_License\\_Manager\\_4\\_11\\_3.zip](https://service.morphotrak.com/content/software/License%20Manager/Morpho_License_Manager_4_11_3.zip)**



MorphoWave™ Compact



April 2018




Open up Morpho License Manager by doing a search or

Go to Start>all program>Morpho>Morpho License Manager 4.X.X>GUI

Or Start typing Morpho license Manager or License in Windows search bar

## Plug in MSO to PC






First step is to get the License ID from the reader.


## By Using Morpho License Manager

Right click  
inside the  
white box  
and Select  
a Morpho  
Access






## Put in the IP address of the reader





## Highlight the Serial numbers



Right Click on the Serial: Copy to Clipboard

Save it to Notepad and email to support




**Once Idemia receives the serial number we will generate the license and email it back to you. Save the License on your PC or Flash drive.**



# To add the License open up Morpho License Manager


Right click inside the white box and Select a Morpho Access







## Put in the IP address of the reader





# Add License

Morpho License Manager - service version: v. 4.11.3 - standalone delivery

Installed License

- No licence available -


Details ...

- [-] SOFTWARE LICENSE
  - Serial: 2010-\*16DYVMZVZW69NDA
  - License: [No license available]
- [-] Morpho Access
  - Serial: 293645695-18152510346-04106006283
  - License: MA\_WIFI;MA\_PAC;MA\_1M\_LOGS;MA\_TA;MA\_3G;MIMA;VERIF;BCL



Close Add License

Click on Add License





**Browse to the location of the file**



**Highlight the License(Lic) and click on Open**



Morpho License Manager - service version: v. 4.11.3 - standalone delivery

**Installed License**


- No licence available -

**Details ...**

- [-] **SOFTWARE LICENSE**
  - Serial: 2010-\*16DYVMZVZW69NDA
  - License: [No license available]
- [-] **Morpho Access**
  - Serial: 293645695-18152510346-04106006283
  - License: MA\_WIFI;MA\_PAC;MA\_1M\_LOGS;MA\_TA;MA\_3G;MIMA;VERIF;BCL

Close    Add License

You will see your new license added





# Website

**Please visit our website,  
[Service.morphotrak.com](http://Service.morphotrak.com) for software,  
firmware, videos and PDF's.**

MorphoWave™ Compact

April 2018