

How to update Sigma/ Sigma  
Lite/ MWC readers with the  
Morpho Tool Box


Please download the Morpho Tool box

4.X.X

Obtain the Tool Box here

<http://service.morphotrak.com/software-links.html>

After you have install the Morpho Tool box click on the Fifth Icon



# Click on the third tap over to Firmware Upgrade

IDE MIA

Diagnostic Compare Configuration **Firmware Upgrade** Image Capture Usb Script Read Script Response Configuration USB script

Put in the IP address of the reader and click browse to upgrade

Firmware Upgrade Settings

File Name  Browse

Address type  IP4  IP6  Host Name

Address

Timeout  Seconds [10-30]

Upgrade

## Things to be aware.

If the reader is in a L1 Legacy mode you will **not** be able to communicate to the reader with the Morpho Tool Box but can go to the firmware tab to upgrade or change it back to its Native mode.

Make sure you have a stable network while doing a firmware upgrade

# Website

- Please visit our website,  
[Service.morphotrak.com](http://Service.morphotrak.com) for software,  
firmware, videos and PDF's.